Output Information Name (Output Information Code)									Application for Cargo Discharge Permission cation Information (Application for Cargo Dis		
Item No.	Column	Field name	Attribute	Length Repeat 1 Repeat 2				Туре		Code	Output Condition/Format
1		Output Common Field	an	398			М				Output the following item in the mail subject. Procedure Code: 5 digits Application for Cargo Discharge Permission Number: 11 digits (*) Output the Application for Cargo Discharge Permission Number in DNC procedure only if the error B/L Number doesn't exist.
2		Procedure Code	an	5			М			Procedure Code	(1) Output "DNC△△" for DNC procedure. (2) In the case of the CDE01 procedure, Output "CDE01" for CDE01.
3		Internal Procedure Code	an	5			М			Procedure Code	Output "1DN△△". (*) To verify the contents of the Process Result Code, refer to the list of procedure messages for "1DN" procedure.
4		Vessel Code	an	9			М			Call sign	(1) Output [Vessel Code] entered for DNC procedure. (2) Output [Vessel Code] registered in the Application for Cargo Discharge Permission DB for CDE01 procedure.
5		Voyage Number	an	10			М				(1) Output [Voyage Number] entered for DNC procedure. (2) Output [Voyage Number] registered in the Application for Cargo Discharge Permission DB for CDE01 procedure.
6		Carrier Code	an	4			М				(1) Output [Carrier Code] entered for DNC procedure. (2) Output [Carrier Code] registered in the Application for Cargo Discharge Permission DB for CDE01 procedure.
7		Port of Discharge Code	an	5			М			UN/LOCODE	(1) Output [Port of Discharge Code] entered for DNC procedure. (2) Output [Port of Discharge Code] registered in the Application for Cargo Discharge Permission DB for CDE01 procedure.
8	100	Process Result Code	an	15			С			Process Result Code	(1) Output [Process Result Code] determined by the system. (2) Output [Process Result Code] entered for DNC procedure. (3) Output [Process Result Code] registered in the Application for Cargo Discharge Permission DB for CDE01 procedure. (*) To verify the contents of the Process Result Code, refer to the list of procedure messages for "1DN" procedure.
9	*	B/L Number	an	35			М				(1) Output the error B/L Number for DNC procedure, (2) If there is no error B/L Number in DNC procedure, output "NON" in the beginning of the repeated messages. (3) Output [B/L Number] to be requested again for CDE01 procedure.